

## Application Window doesn't appear

Kamel Balquis - 2025-03-25 - Comments (0) - Known Issues & Solutions

In some scenarios, Windows doesn't disconnect External monitors, causing the Application's Window to not be displayed.

Steps to reproduce:

- Open Application while computer is connected to one or more external monitors.
- Exit Application
- Disconnect one or more external monitors.
- Open application
- Application's appears in Windows Taskbar, but the Application's Window doesn't show.

There are different solutions for this, depending on the Application.


For Visual SuperChems™ :

- Open the folder C:\iOiQ\PSOx.y\SuperChems\GUI\Files. Where **x.y** is the Process Safety Office® version installed.
- Delete the file 'config.xml' and open Visual SuperChems™.
- Open Visual SuperChems™, The Application's Window should appear.

For Visual SuperChems™ and Piping Layout Editor:

If this doesn't work, please try the following:

- Open the relevant Application.
- When the application is in the Taskbar, hover the mouse over the application's icon.
- When the window appears, right-click on it, and select 'Move'



- Using your **keyboard**, press any of the Arrow keys (up, left or right arrow keys) twice.
- Without clicking your Mouse, move the mouse on the screen, the Application's Window will appear.

If both solutions do not work, please contact [ioiqhelpdesk@iomosaic.com](mailto:ioiqhelpdesk@iomosaic.com) or submit a ticket through <https://support.iomosaic.com/new-ticket> and our support team will help you resolve the issue.